

Colibri firmware upgrade manual.

1. Connect USB-Tracker (dongle) to your Windows-PC
2. Launch Colibri GUI. F/W column will show firmware version (fig1.).




Fig. 1 – Colibri GUI

3. Close Colibri GUI and launch Terminal (for example terminal 1.9b by Bray).
 4. Look in your Windows Device Manager which COM Port the tracker got.
-

5. Select this COM port in your terminal, and set Baud rate 9600, data bits 8, Parity none, Stop bit 1. Like on fig. 2.




Fig. 2 - COM Port settings

6. Push “Connect” to connect your terminal with your tracker.
7. Send "f" in order to upgrade firmware. You will see follow answer message (fig. 3):

“Press [y] to update firmware

(This will save current settings also!)”




Fig. 3 – message from device before update firmware.

8. Send “y” in order to confirm upgrade firmware.
9. In your explorer comes a new drive with the name "Firmware"
10. Drag your latest firmware to this drive.
11. If firmware successful, “Firmware” drive will disappear.
12. Disconnect tracker(dongle).

Contact information

Trivisio

Internet: www.trivisio.com

Email: info@trivisio.com
